

ITH-Valentine-Pocket-5x7-NLS

Instructions



Great
container for
Candy.



Gift
Container.



Great container to use to give a
money gift.




Materials/Cutting Chart

Materials	Number of Cuts & Size
Fabric Front	1 cut at 5 x 6 inches
Fabric Back & Lining	2 cuts at 5 x 7.75 inches
Heat-N-Bond Lite	1 cut at 5 x 7.75 inches 1 cut at 5 x 6 inches
Puffy Foam	1 cut at 6 x 7.75 inches
Kam Snaps	1 set
Water Soluble Stabilizer	Enough for a 5 x 7 inch hoop



The Color Sequence Chart below will be referenced throughout these instructions.

Color Sequence:



Printed by Generations(TM), Copyright 2002-2007, All Rights Reserved.


<p>1. Prepare materials as indicated in the Materials/Cutting Chart above.</p> <p>Lining and back fabric pieces</p> <p>Heat-N-Bond Lite pieces</p> <p>Front fabric piece</p> <p>Puffy Foam piece</p>	
--	--

2. Fuse the two fabric pieces (Back & Lining) together with the Heat-N-Bond piece (5 x 7.75 inches) with right sides to the outside.
3. Fuse the 5 x 6-inch Heat-N-Bond Lite piece to the back of the front fabric piece.

Back fabric piece fused to the lining piece with Heat-N-Bond

Puffy Foam piece


Front fabric piece with Heat-N-Bond fused to the back



4. Hoop the water-soluble stabilizer in a 5 x 7 inch embroidery hoop and attach to embroidery machine.
5. Transfer the design file (NLSEE1608-5x7) to your embroidery machine.



6. Sew #1 in the Color Sequence Chart. These stitches will create the placement stitches for the front of the project. The placement stitches are difficult to see because they were sewn in white, but they will be visible for you when you sew them.



7. Remove hoop from machine and place the Puffy Foam piece over the placement stitches. Secure at top and bottom with tape.
8. Return hoop to machine and sew #2 in the Color Sequence Chart. These stitches will attach the foam to the stabilizer.



9. Remove hoop from machine and carefully cut away excess foam from the project.



10. Remove the Heat-N-Bond paper backing from the front fabric piece.



11. Place the front, fabric, piece, heat-N-Bond-side down over the foam and secure at the top and bottom with tape.



12. Return hoop to machine and sew #3 in the Color Sequence Chart. These stitches will attach the front-fabric-piece to the project.



13. Sew #4 in the Color Sequence Chart. These stitches will create the floral design around the outside of the project.




14. Change bobbin thread to match whatever color thread you will use for the outside border and change the needle thread to match the bobbin.

15. Remove hoop from machine and carefully cut away the fabric at the top of the front, as indicated in the photo.



16. Return hoop to machine and sew #5 in the Color Sequence Chart. These stitches will create the satin border at the top of the front of the project.



17. Sew #6 & #7 in the Color Sequence Chart. These stitches will create the front design.



18. Remove hoop from machine, turn upside-down on a flat surface and clip all thread tails from the back of the hoop.
19. Place the back piece fused to the lining over the back of the hoop. Line up the bottom with the front piece and tape in place at all four corners.

Back of Hoop



20. Return hoop to machine and sew #8 in the Color Sequence Chart. These stitches will attach the back/lining piece to the project.



21. Remove hoop from machine and carefully cut away excess fabric from the back of the hoop.



22. Turn hoop to right side and cut away excess fabric from the front of the project.



23. Return hoop to machine and sew #9 in the Color Sequence Chart. These stitches will create the satin border around the outside of the project.




24. Remove hoop from machine and carefully cut away the stabilizer on front of the project-(stabilizer between the top of the project and the top of the front as shown in photo.



25. Remove project from hoop and cut away stabilizer from around the project. Leave ¼ inch around the outside of the project to prevent cutting satin border.

¼ inch of stabilizer



26. Select Kam Snaps to match the fabric.



27. Find the center of the top, fold-down, piece and use the tool to create a hole in the flap.



28. Place the Kam Snap pieces in the hole and attach with the tool.



29. You need to find the centered placement for the second part of the snap set. I use soap on the flap snap, fold and tap to transfer the soap to the front section.

Put soap here-pretty thick, so it will show up when transferred.



30. Use the attachment tool to place the second part of the snap set.



31. Remove remaining stabilizer from around the project (the ¼ inch you left in step 24).



32. Also remove the stabilizer left when you cut away the stabilizer from this area. —————→



33. Use clip (or pins) to hold the flap in place while the edges dry and your project is complete.

